

Data-Miner 7.1 Installation for z/VSE

Data-Miner is usually distributed by email or as a download from the CSI Website:

<http://www.csi-international.com/>

There is one file attached to the email, either as ready-to-use file or as a single ZIP archive that you need to unzip.

The file is

DM71AV.BJB

It contains a single Power job to install Data-Miner into a library. After it is installed, you can move the different phases into libraries of your choosing.

Data-Miner Manual

User Reference Guide

The Installation Job

The Data-Miner installation job is a Power job in card image format. Review it and make any changes that are necessary for the job to run at your installation. These may include changing the jobname and class. There is a PAUSE in the job that asks you to enter the value for the SUBLIB parameter to name the library into which Data-Miner should be installed. Feel free to change this to a LIBDEF or to separate LIBDEFs for the relocatable module and the phases.

The installation job installs a single relocatable module (*VNATB*), the Data-Miner batch phases (*CSIDMBMD* and *VNATB2*), and the online CICS phases (*VNAT* and *CSIDMOMD*). Data-Miner does not use any BMS maps.

Finishing Installation for CICS

After you have the load modules restored to a load library, you need to install them into your CICS system using CEDA. You can move the modules to a load library that is in the CICS load library concatenation if you like – the only two load modules needed for CICS are *CSIDMOMD* and *VNAT*.

Both programs are written in assembler and can be put into any group you like. You can also use any transaction ID that you like—the default is MINE, which is used in the manual. Neither program needs a TWA.

Note: *VNAT* must be installed to run with EXECKEY=CICS.